

Emu Egg Incubating Directions - # 2

for G.Q.F. auto-rotate incubator

1. Temperature - 97.5
2. Humidity - 30% - 32%
3. Manually flip eggs twice daily [wear disposable gloves]. Eggs should be set with ID tape on the side. Turn LEFT in morning / RIGHT at night, with tape side up while turning.
4. Level shelves using toggle switch on left top side of incubator.
5. After shelf is level, lift and pull out to flip eggs, hold tray, do not drag tray over springs at front of shelf.
6. Make sure shelves are pushed all the way back into incubator after manual rotation. Rotate shelves top to bottom, middle to top and bottom to middle.
7. Add water to pans to keep full unless humidity is very high.
8. Have all 6 vents in back of incubator at least half open.
9. Smell air when you open incubator, bad smell indicates bad egg. Find bad egg (smell them all) and remove.
10. Look for "bumps" or "brown oozing" on eggs. This is an indication of a bad egg. Remove egg.
11. After removing bad egg, spray incubator and remaining eggs with bleach water.
12. Manually rotate shelves so they are on an angle.
13. Set shelves to rotate automatically. [RED indicator light is on. This light is on the left rear side of the incubator]
14. Contact _____ phone number _____ at any time with any questions.
